

How to - Corus Evo+

How to save DT all files for debug

815-0000-12

AA

1. Run **Wincor Evo** software in **Standard** mode.




- a. From **Device configuration** select **Parameters from device**.



- b. Select **Data reading** and **All data to *.dt_all file**.



- c. When completed a new window will pop up which shows the location of the *.dt_all file. Use the **copy to clipboard** button for easy copy and paste into an email etc.



Dresser Utility Solutions GmbH

Hardeckstr. 2
76185 Karlsruhe
T: +49 (0)721 / 5981 - 0
info.karlsruhe@dresserutility.com



© 2026 Dresser Utility Solutions GmbH – All rights reserved. Dresser Utility Solutions reserves the right to make changes in specifications and features shown herein, or discontinue the product described at any time without notice or obligation. Contact your Dresser Utility Solutions representative for the most current information. The Dresser Logo and all Trademarks containing the term "Dresser" are the property of Dresser, LLC, a subsidiary of Baker Hughes. Actaris™ is a trademark owned by Itron, Inc. and used under license.

815-0000-12 AGM How to save DT all files and debug DUS.AGM.EN.AA
06.26